

When I load the CD I have problem viewing the menus (dropdown lists) across the top and down the left hand column. I cannot make the CD ROM work. Am I doing something wrong?

No, it would appear that your Adobe Flash Player may require you to reset your flash player global security settings. Some machines will give you a warning telling you that it is trying to communicate with the CD in the drive and ask you to increase the security, if you say yes, you will automatically open up a page on the web site to allow you to do this. If the program doesn't prompt you, you can access it by going to the link below.

http://www.macromedia.com/support/documentation/en/flashplayer/help/settings_manager04.html

Adobe Flash Player™ Settings Manager

Global Security Settings

Some websites may access information from other sites using an older system of security. This is usually harmless, but it is possible that some sites could obtain unauthorized information using the older system. When a website attempts to use the older system to access information:

Always ask Always allow Always deny

Always trust files in these locations:

d/

Note: The Settings Manager that you see above is not an image, it is the actual Settings Manager itself. Click the tabs to see different panels, and click the options in the panels to change your Adobe Flash Player settings.

If you are a designer or developer creating applications for Flash Player, see Global security settings for content creators instead.

Use the Global Security Settings panel to specify if Flash content that uses older security rules can access the Internet. (For information about why you may need to do this, see What are security settings?) To help you decide if it is safe to allow the older security rules to be used, ask yourself: Did I originally download this content myself from a website that I trust? Is the Flash content trying to communicate with a website that I trust? The website with which the Flash content wants to communicate is listed in the pop-up dialog that appears when the Flash content first tries to communicate with the website.

Your options are as follows:

- You can set Flash Player to always **ask** your permission before letting Flash content use older security rules; always **allow** Flash content to use older security rules; or always **deny** Flash content the right to use older security rules. These options, at the top of the panel, apply to both Flash content that you use on the Web and that is stored locally on your computer. Read more about Online and local content that uses the older security rules, below.
- (Flash Player 6 and later only) For a finer level of control, you can let specific Flash content use older security rules. To learn more, click the "Always ask" button.

FEEDBACK

There is a box called adobe flash settings manager and right underneath the box it says

Note: The Settings Manager that you see above is not an image; it is the actual Settings Manager itself. Click the tabs to see different panels, and click the options in the panels to change your Adobe Flash Player settings.

You are going to reset your global security settings to allow the CD to work by following the instructions.

- Click on the arrow beside “edit Locations”
- Select and click “add locations”
- In the white box under trust this location enter the CD drive name (I entered the drive it needed to look in which was my Cd ROM drive D:/)
- Press confirm. Shut down and restart CD